Sankyo

DRIVER SPECIFICATION

Type Name :

ICT3K5-6290DLL

Spec. No. ASL-NP-07652-52

Notes:

SGH Distribution र् Revision Page Sym. Cha. No. Date Appr. Reference Document M.Kimura Design Mar. 1. '05 T.Komatsu Mar. 4. '05 Det-che ICT3K5-3R6290 Sankyo Seiki Mfg.Co.,Ltd. Y.Uemura Mar.04.2005 Type Name Appro.

REGISTERED MAR. 7.2005 ENG. DIV

No. S39Z-032-00-02C

Revision History on the Document

Revision	Date	Ву	Descriptions
Α	March 1, 2005	Masanori.Kimura	Newly issued

Contents

1.	G	enerals	. 2
	1.1 1.2	Scope Conventions of Descriptions in This Document	
	1.3	·	
2.	D	evelopment Environment	. 4
;	2.1	DLL	4
;	2.2	Application Programs	4
3.	E	xecution Environment	. 5
;	3.1	Host Computer	5
;	3.2	OS (Operating System)	5
;	3.3	Language	5
4.	G	eneral Functions	. 6
	4.1	File Structure	
		4.1.1 Files and their main functions	
		4.1.2 Use of the files	
		4.1.3 Kernel driver	
•	4.2	Specifications	
		4.2.1 The number of Card Reader/Writers that can be controlled at the same time	
		4.2.2 Data definition	
		DLL_INFORMATION	
		COMMAND	
		REPLY	
		RESULT_TYPE	
		POSITIVE_REPLY	
		NEGATIVE_REPLY Examples of Command Execution Results to be Stored in REPLY	
		4.2.3 APIs	
		GetDIIInformation	
		ConnectDevice	
		DisconnectDevice	
		CancelCommand	21
		ExecuteCommand	23
		ExecuteCommand2	27
		ICCardTransmit	28
		SAMTransmit	33
		UpdateFirmware	38
		4.2.4 Log file	43
Th	e e	nd of this document	44

1. Generals

1.1 Scope

This specification document intends to define the functions, contents, and restrictions regarding the dynamic link library: ICT3K5-6290DLL, which controls the Card Reader/Writer: ICT3K5-3R6290 produced by Sankyo Seiki Mfg. Co., Ltd.

You should understand that, in general, any functions and/or matters that are not described in this document cannot be implemented or their operation results are insecure.

1.2 Conventions of Descriptions in This Document

Unless otherwise especially noted; "Card Reader", "Card Reader/Writer", "Target", "Device", "Target Device" and other equivalents shall all be understood to be the Card Reader/Writer mentioned in "1.1 Scope".

In this document, Dynamic Link Library is simply called "DLL" as commonly abbreviated. You should understand, therefore, that mentioning "the DLL" without any special note points out the dynamic link library mentioned in "1.1 Scope".

"Application Program" or "Application" in short generally means a program(s) that controls the Card Reader/Writer(s) through the DLL. These expressions can be replaced with "Program using the DLL".

"API" stands for "Application Programming Interface". By using APIs, the Application Program makes use of the functions, which the DLL serves.

The functions, which the DLL serves, are materialized as "Commands". The Application Program makes use of the DLL by calling the commands (functions). Professional-wise, such operations may be described sometimes as; "The DLL exports functions and the Application Program imports the DLL functions."

As mentioned above, the substance of API is functions so that API is sometimes called "API functions".

"Host Computer" or "Host" in short is connected to the Card Reader/Writer(s) with cable, and it is a computer that controls and operates the Card Reader/Writer(s) by executing the DLL or the Application Program using the DLL.

"OS" stands for "Operating System".

"Installation of the Card Reader/Writer" or "Installing the Card Reader/Writer" means to carry out a series of preparation work such as; installing the Card Reader/Writer, connecting it to the Host Computer, supplying it with electrical power in order that the Host Computer can control the Card Reader/Writer.

"To control the Card Reader/Writer" means to send commands from the Host Computer for making the Card Reader/Writer execute the specified functions and to eventually have the Host Computer receive the corresponding response so that the Host Computer initiatively controls the Card Reader/Writer to implement the Card Reader/Writer functions.

No

"API call" or "Calling API" means "API execution" or "Executing API", and they are used to mean just the same thing and can be replaced with each other.

When any related publication(s) or article(s) to be referred to is pointed out in any section other than explanatory parts, a rightward arrow " " is placed at the top of the indication.

1.3 Notice

Sankyo Seiki Mfg. Co., Ltd. is exempt from any responsibilities, for damages on your system including the host computer(s) and network system, which might have been caused due to installing or using the DLL. Before using the DLL, therefore you are requested to check the operation of the DLL and make sure of the operation contents to ensure that there should occur no problem due to operation of the DLL.

Microsoft, Windows XP, Visual C/C++6.0 are all trademarks of the Microsoft Corporation, USA.

2. **Development Environment**

2.1 DLL

The DLL is built under the development environment described below: Microsoft Visual C/C++6.0

2.2 Application Programs

The DLL is coded by using the C++ language. It has already been made sure that the DLL is rightly linked to an application program, built under the same development environment as what the DLL has been built under, and it operates properly.

No

It has not been checked whether or not the DLL can rightly function when an application program developed under any different environment tries to use the DLL.

3. Execution Environment

3.1 Host Computer

IBM PC/AT compatible machine equipped with one or more USB port(s)

3.2 OS (Operating System)

Microsoft Windows XP

3.3 Language

The DLL operates, being irrelevant to the language specifications of the operating system. In other words, the language specifications of the operating system do not affect the basic operation of the DLL.

The DLL is provided with just one type of resource; i.e., English one, and therefore even if the operating system of the execution environment is not English version, every message is given in English.

4. General Functions

4.1 File Structure

4.1.1 Files and their main functions

Files	Main functions
[1] ICT3K5_6290DLL.dll	This file is an execution module of the DLL. It serves each API's execution code. This file is needed when the Application Program is executed. Revision:2650-01B
[2] ICT3K5_6290DLL.lib	This file is needed when the Application Program, to which the DLL is implicitly linked, is created. It serves information on APIs exported by the DLL. It is not needed when linking is made explicitly.
[3] ICT3K5_6290DLL.h	It is a header file to serve API type declarations, error code definitions and so on. It is needed when the Application Program is created.
[4] PrtclUH.dll	It is a DLL file that operates at a lower layer under the file [1] to serve more fundamental functions. It is needed for executing the file [1]. Revision:2566-01C
[5] CollectLogEx.dll	It is a DLL file that operates at a lower layer under the file [4] to create log files. Revision:2509-02A

4.1.2 Use of the files

The DLL files (.dll) are found and loaded at the time of executing the Application Program according to the procedures and rules specified by the operating system. Therefore, the condition on the folders, in which the DLL files are installed, shall meet the specifications of the operating system.

The files required at the time of developing the Application Program shall be used according to the specifications of the development environment.

4.1.3 Kernel driver

The DLL communicates with the Card Reader/Writer by using a class driver bundled in the operating system. Therefore, it is not needed to install any special kernel driver for executing the DLL.

4.2 Specifications

4.2.1 The number of Card Reader/Writers that can be controlled at the same time

It is possible to boot multiple threads from a process, i.e., the Application Program, for which the DLL is mapped, and to make each thread control each different target.

No

In the specifications of the DLL, there is no restriction on the number of Card Reader/Writers that can be controlled at the same time.

The resource, which is needed to control a Card Reader/Writer, is dynamically secured as required so that there is theoretically no restriction on the number of Card Reader/Writers that can be controlled. However, practically there appears some restriction due to the specifications of the USB interface and/or the restrictions of resource of the host computer.

4.2.2 Data definition

This section describes the original data types used in the DLL.

The data types, which this section describes, are all defined in the header file (.h); one of the configuring files.

Refer to the file [3].

DLL_INFORMATION

DLL_INFORMATION is used when GetDllInformation is executed. Each member stores the information described below:

Members		Descriptions
upperDll	szFilename[]	Character string to indicate the filename of the file [1].
	szRevision[]	Character string to indicate the revision number of the file [1].
lowerDll	szFilename[]	Character string to indicate the filename of the file [4].
	szRevision[]	Character string to indicate the revision number of the file [4].

Refer to GetDllInformation.

COMMAND

```
typedef struct
{
    BYTE    bCommandCode;
    BYTE    bParameterCode;

    struct
    {
        DWORD    dwSize;
        LPBYTE    lpbBody;
    }
    Data;
}
COMMAND, *LPCOMMAND;
```

COMMAND is used for the purpose of giving the materials needed to compose a command message when calling ExecuteCommand, i.e., a command code, a parameter code, and data.

Members		Descriptions
bCommandCode		Command code
bParameterCode		Parameter code
Data dwSize Size of the data (bytes) If there exists no data to give, set dwSize to be 0.		Size of the data (bytes) If there exists no data to give, set dwSize to be 0.
	lpbBody	Pointer to the memory area where the data is saved If dwSize is 0, then lpbBody is ignored.

Refer to ExecuteCommand, ExecuteCommand2.

Regarding the structure of a command message, refer to the specifications of Card Reader/Writer Interface.

REPLY

```
typedef struct
{
    REPLY_TYPE replyType;

    union
    {
        POSITIVE_REPLY positiveReply;
        NEGATIVE_REPLY negativeReply;
    }
    message;
}
REPLY, *LPREPLY;
```

REPLY is used for the purpose of saving the execution results and contents of the command executed by calling ExecuteCommand.

Members		Descriptions
ReplyType		Execution results of the command
		Refer to REPLY_TYPE.
	PositiveReply	Contents of the execution results in the case of
		"replyType = PositiveReply"
		Refer to POSITIVE_REPLY.
message	NegativeReply	Contents of the execution results in the case of
		"replyType = NegativeReply"
		Refer to NEGATIVE_REPLY.

Refer to REPLY_TYPE, POSITIVE_REPLY, NEGATIVE_REPLY, ExecuteCommand, ExecuteCommand2, UpdateFirmware, ICCardTransmit, SAMTransmit.

REPLY_TYPE

```
typedef enum
{
    PositiveReply,
    NegativeReply,
    ReplyReceivingFailure,
    CommandCancellation,
    ReplyTimeout,
}
REPLY_TYPE, *LPREPLY_TYPE;
```

REPLY_TYPE is used for member declaration of the data definition: REPLY, and indicates the execution results of the command notified by response message.

Definitions	Descriptions
PositiveReply	Positive response has been returned.
NegativeReply	Negative response has been returned.
ReplyReceivingFailure	Response receiving has failed.
CommandCancellation	In the condition of waiting for response receiving, CancelCommand has been executed and command execution has been canceled.
ReplyTimeout	In the condition of waiting for response receiving, time-out has occurred.

Refer to REPLY.

POSITIVE_REPLY

```
typedef struct
{
    BYTE bCommandCode;
    BYTE bParameterCode;

struct
    {
        BYTE bSt1;
        BYTE bSt0;
}
    StatusCode;

struct
    {
        DWORD dwSize;
        BYTE bBody[ MAX_DATA_ARRAY_SIZE];
}
    Data;
}
POSITIVE_REPLY, *LPPOSITIVE_REPLY;
```

POSITIVE_REPLY is used for member declaration of the data definition: REPLY, and it is used for storing the execution results of the command when a positive response is received.

Members		Descriptions
bCommandCode		Command code
bParameterCode		Parameter code
StatusCode	bSt1	Status code: st1
	bSt0	Status code: st0
Data	dwSize	Size of the data (bytes) given by the response message.
	bBody[]	Stores the data body given by the response message.

Refer to REPLY and NEGATIVE_REPLY.

Regarding the structure of a positive reply message, refer to the specifications of Card Reader/Writer Interface.

NEGATIVE_REPLY

```
typedef struct
{
    BYTE bCommandCode;
    BYTE bParameterCode;

struct
    {
        BYTE bE1;
        BYTE bE0;
    }
    ErrorCode;

struct
    {
        DWORD dwSize;
        BYTE bBody[ MAX_DATA_ARRAY_SIZE];
    }
    Data;
}

NEGATIVE_REPLY, *LPNEGATIVE_REPLY;
```

NEGATIVE_REPLY is used for member declaration of the data definition: REPLY, and it is used for storing the execution results of the command when a negative response is received.

Members		Descriptions
bCommandCode		Command code
bParameterCode		Parameter code
ErrorCode	bE1	Error code: e1
	bE0	Error code: e0
Data	dwSize	Size of the data (bytes) given by the response message.
	bBody[]	Stores the data body given by the response message.

Refer to REPLY and POSITIVE_REPLY.

Regarding the structure of a negative reply message, refer to the specifications of Card Reader/Writer Interface.

Examples of Command Execution Results to be Stored in REPLY

Example 1) In the case of Positive Response

If the contents of the response message, which returns as the results of executing the command by calling ExecuteCommand, are as described below; ...

Type of response		Positive response
Command code		12h
Parameter code		34h
Ctatus ands	st1	35h (= `5')
Status code	st0	36h (= '6')
Data		A1h, A2h, A3h, A4h, A5h (5 bytes)

... contents of the response message are saved into the REPLY type data specified by ExecuteCommand.

.reply	уТуре	PositiveReply
.messa	age	
	positiveReply	
	.bCommandCode	12h
	.bParameterCode	34h
	.StatusCode	
	.bSt1	35h
	.bSt0	36h
	.Data	
	.dwSize	5
	.bBody[]	Alh, A2h, A3h, A4h, A5h

Example 2) In the case of Negative Response

If the contents of the response message, which returns as the results of executing the command by calling ExecuteCommand, are as described below; ...

Type of response		Negative response
Command code		12h
Parameter code		34h
Francisco do	e1	35h (= `5')
Error code	e0	36h (= '6')
Data		None

... contents of the response message are saved into the REPLY type data specified by API.

.replyType			NegativeReply
.message			
	.negativeReply		
	.bCo	ommandCode	12h
	.bPa	rameterCode	34h
	.Err	rorCode	
		.bE1	35h
		.bE0	36h
	.Data		
į		.dwSize	0
		.bBody[]	No data storing

Refer to ExecuteCommand, ExecuteCommand2.

No

4.2.3 APIs

GetDIIInformation

```
DWORD GetDIIInformation(

LPDLL_INFORMATION IpDIIInformation
);
```

Function

Obtains information on the DLL.

Argument & Detailed Function

IpDIIInformation

Information on the DLL is saved in the data set of <code>DLL_INFORMATION</code> type to get notified in the format.

Refer to DLL_INFORMATION.

This API can be executed anytime, regardless of completion of ConnectDevice. Even if this API is executed, no communication transaction between the Host Computer and Card Reader/Writer (such as "Command sending – Response receiving") is caused.

Return Value

_NO_ERROR

The return value of this API is always _NO_ERROR.

Example

```
DLL_INFORMATION dllInformation;
GetDllInformation(
    &dllInformation
);
```

ConnectDevice

Function

Makes preparations for controlling the Card Reader/Writer(s). The key operations are as described below:

To set up communication between the Host Computer and Card Reader/Writer To secure and initialize the resource for controlling the objective Card Reader/Writer Refer to DisconnectDevice.

Argument & Detailed Function

IpszSerialNumber

Specify the serial number of the Card Reader/Writer for which communication is set up. The serial number shall be a character string having a NULL at the end.

If only one Card Reader/Writer exists, you might as well specify it with a NULL instead of the serial number.

If a NULL is specified even though two or more Card Reader/Writers exist, it becomes impossible to identify which Card Reader/Writer is the target one so that operation may not work on the Card Reader/Writer you want but work on another one. In such a case, therefore it is prohibited to specify a NULL.

IpszCurrentSerialNumber

Once the API implementation succeeds, the serial number of the Card Reader/Writer, for which communication has been set, gets returned. The serial number to be returned at the time is expressed as a character string having a NULL at its end. Then, the serial number is saved in the address specified with <code>lpszCurrentSerialNumber</code>, and it is reported to the Application Program.

For the serial number storage, it is recommended to secure a memory area of 16 bytes or greater. Regarding the serial number and the size of the memory area required for saving the serial number, refer to the specifications of Card Reader/Writer Interface.

Even if communication is set with <code>lpszSerialNumber = NULL</code>, the serial number of the objective Card Reader/Writer can be noted by using <code>lpszCurrentSerialNumber</code>. To execute any API such as <code>ExecuteCommand</code> and <code>CancelCommand</code>, which requires specifying a serial number, set the serial number obtained in this manner.

For execution of any API operation accompanied by communication transaction, it is needed to complete ConnectDevice in advance.

Return Value

_NO_ERROR

Normally completed

_CANNOT_CREATE_OBJECT_ERROR

Failed in creating the object

_CANNOT_OPEN_DRIVER_ERROR

Failed in opening the driver

This error may be caused in the cases described below:

The specified Card Reader/Writer is already in operation.

The specified Card Reader/Writer is not installed yet.

The communication driver cannot get opened due to any other reason.

_FAILED_TO_BEGIN_THREAD_ERROR

Failed in creating or invoking a thread.

_DEVICE_ALREADY_CONNECTED_ERROR

ConnectDevice is already completed.

Example

19/44

DisconnectDevice

Function

Quits controlling the Card Reader/Writer. The key operations are as described below:

To quit communication

To release the resource secured for controlling the objective Card Reader/Writer Refer to ConnectDevice.

Argument & Detailed Function

IpszSerialNumber

Specify the serial number of the objective Card Reader/Writer. The serial number shall be a character string having a NULL at the end.

Refer to ConnectDevice.

Once this API is executed, it becomes impossible to control the objective Card Reader/Writer. When it becomes necessary to control the Card Reader/Writer, execute ConnectDevice again.

When it becomes unnecessary to control the Card Reader/Writer, for example, at the time of quitting the Application Program; be sure to execute DisconnectDevice as a quitting operation.

If Plug & Play occurs in the process and it requires you to execute ConnectDevice again, execute DisconnectDevice first and then execute ConnectDevice.

Return Value

_NO_ERROR

Normally completed

DEVICE NOT CONNECTED ERROR

This error may be caused in the cases described below:

ConnectDevice operation is not yet completed for the specified Card Reader/Writer.

DisconnectDevice operation is already executed for the specified Card Reader/Writer.

20/44

```
{
    // ConnectDevice completed
    ...
    // Closes communications
    DisconnectDevice( szSerialNumber);
}
```

if(dwResult == _NO_ERROR)

CancelCommand

Function

Cancels the command being in operation. The key operations are as described below:

To send "DLE,EOT" control code and receive the response

To cancel the condition of waiting for the response if there exists ExecuteCommand waiting for response to the command

Argument & Detailed Function

IpszSerialNumber

Specify the serial number of the objective Card Reader/Writer. The serial number shall be a character string having a NULL at the end.

Refer to ConnectDevice.

Being executed, this API sends "DLE,EOT" control code to the Card Reader/Writer. Once having received "DLE,EOT" control code while executing a command, the Card Reader/Writer interrupts the command execution and returns a response. The API waits for receiving the response, and it returns the control to the Application Program when the response reception is confirmed. Regarding the "DLE,EOT" control code and operation of Card Reader/Writers at the time when the Card Reader/Writer receives the code, refer to the specifications of Card Reader/Writer Interface.

To execute this API, ConnectDevice must have already been completed.

Refer to ConnectDevice.

If there exists ExecuteCommand waiting for response to command execution, executing CancelCommand from another thread cancels the condition of waiting for response so that the ExecuteCommand quits the execution and returns the control to the Application Program.

Refer to ExecuteCommand.

Return Value

_NO_ERROR

Normally completed

_DEVICE_NOT_CONNECTED_ERROR

ConnectDevice operation is not yet completed for the specified Card Reader/Writer.

Refer to ConnectDevice.

_FAILED_TO_SEND_COMMAND_ERROR

"DLE,EOT" cannot be sent.

When an error has happened in the layer that operates under the DLL to serve further basic functions to the DLL, this error code is returned.

CONFIDENTIAL No ASL-NP-07652-52 22/44

_FAILED_TO_RECEIVE_REPLY_ERROR

An error has happened in the operation of receiving the response for "DLE,EOT" control code. When an error has happened in the layer that operates under the DLL to serve further basic functions to the DLL, this error code is returned.

_REPLY_TIMEOUT

A time-out error has happened in the operation of receiving the response for "DLE,EOT" control code.

The time-out setup is made to be 5 seconds in this API operation.

Example

CONFIDENTIAL No ASL-NP-07652-52 23/44

ExecuteCommand

Function

Executes a command, and returns the execution result.

Argument & Detailed Function

IpszSerialNumber

Specify the serial number of the objective Card Reader/Writer. The serial number shall be a character string having a NULL at the end.

Refer to ConnectDevice.

Command

Provide the materials needed to compose a command message, i.e., a command code, a parameter code, and data.

Refer to COMMAND.

dwTimeout

Specify the time-out interval for the period from sending the command message until receiving the reply message to it. The interval is specified in millisecond.

If dwTimeout is INFINITE, the function's time-out interval never elapses.

IpReply

Specify the data save destination for the command execution results, and give a pointer to REPLY type data as the save destination.

Refer to REPLY.

To execute this API, ConnectDevice must have already been completed.

Refer to ConnectDevice.

Regarding the details of the command to be executed by calling this API, refer to the specifications of Card Reader/Writer Interface.

Return Value

NO ERROR

Normally completed

_DEVICE_NOT_CONNECTED_ERROR

ConnectDevice operation is not yet completed for the specified Card Reader/Writer.

Refer to ConnectDevice.

CONFIDENTIAL | No | ASL-NP-07652-52 | 24/44

_CANCEL_COMMAND_SESSION_ERROR

Since CancelCommand is now being executed, it is impossible to execute this API. Refer to CancelCommand.

_FAILED_TO_SEND_COMMAND_ERROR

The command cannot be sent.

When an error has happened in the layer that operates under the DLL to serve further basic functions to the DLL, this error code is returned.

FAILED TO RECEIVE REPLY ERROR

An error has been caused in response receiving operation for the executed command. When an error has happened in the layer that operates under the DLL to serve further basic functions to the DLL, this error code is returned.

_COMMAND_CANCELED

The command execution has been canceled.

REPLY TIMEOUT

Time-out has been caused in response receiving operation for the executed command.

Example

```
E.g. 1)
#define _TIMEOUT
                       (20000)
                                  // milliseconds
CHAR szSerialNumber[ 16];
// Establishes communications between the Host Computer and the Card Reader/Writer
// and detects a target device's serial number
DWORD dwResult = ConnectDevice(
                         NULL.
                         szSerialNumber
                         );
COMMAND Command;
                                    // Command message to send
   Command.bCommandCode = 0x31; // Status request command
   Command.bParameterCode = 0x30; // Parameter code
   Command.Data.dwSize = 0;
                                          // Data size
REPLY Reply;
                                     // Reply message to receive
// Executes Status request command, and then receives a reply for the command
dwResult = ExecuteCommand(
              szSerialNumber.
              Command,
              _TIMEOUT,
              &Reply
```

```
if( dwResult == _NO_ERROR && Reply.replyType == PositiveReply)
{
   if(Reply.message.positiveReply.StatusCode.bSt1 == '0'
   && Reply.message.positiveReply.StatusCode.bSt0 == '2')
      // status code="02"
      // Detected a card inside of Card Reader/Writer
   }
}
else
   // Unexpected situation occurred
}
E.g. 2)
#define _SERIAL_NUMBER "12345678" // Target device's serial number
#define _TIMEOUT
                                         // milliseconds
                             (20000)
CHAR szSerialNumber[ 16];
// Establishes communications between the Host Computer and the Card Reader/Writer
DWORD dwResult = ConnectDevice(
                         _SERIAL_NUMBER,
                         szSerialNumber
                         );
COMMAND
               Command;
                             // Command message to send
{
    Command.bCommandCode = 0x30;
                                         // Initialize command
    Command.bParameterCode = 0x30;
                                         // Parameter code
    BYTE fm = 0x30;
    BYTE Pd = 0x30:
    BYTE Wv = 0x30;
    BYTE Sh = 0x30;
    BYTE Ds = 0x30;
    BYTE Ty = 0x31;
    BYTE Cp = 0x30;
    BYTE bData[] = { 0x33, 0x32, 0x34, 0x30, fm, Pd, Wv, Sh, Ds, Ty, Cp, };
    Command.Data.dwSize = sizeof( bData) / sizeof( BYTE); // Data size (bytes)
    Command.Data.lpbBody = bData; // Start address of region where data is saved
}
REPLY Reply; // Reply message to receive
```

```
// Executes Initialize command, and then receives a reply for the command
dwResult = ExecuteCommand(
               szSerialNumber,
               Command,
               _TIMEOUT,
               &Reply
               );
if( dwResult == _NO_ERROR)
  // Initialize command successfully finished.
   if( Reply.replyType == PositiveReply)
      // Received positive reply
  }
   else if( Reply.replyType == NegativeReply)
      // Received negative reply
      ...
  }
else
  // Initialize command failed.
}
```

CONFIDENTIAL No ASL-NP-07652-52

27/44

ExecuteCommand2

```
DWORD ExecuteCommand2(

LPCSTR IpszSerialNumber,

LPCOMMAND IpCommand,

CONST DWORD dwTimeout,

LPREPLY IpReply
);
```

Function

Executes a command, and returns the execution result.

ExecuteCommand and ExecuteCommand2 are identical except for just one point, i.e., in case of ExecuteCommand the second parameter, COMMAND, is given as an instance while the parameter is specified in the format of a pointer when calling ExecuteCommand2.

Refer to ExecuteCommand.

ICCardTransmit

```
DWORD ICCardTransmit(
             LPCSTR
                              IpszSerialNumber.
             COSNT DWORD dwDataSizeToSend,
             LPBYTE
                             IpbDataToSend,
             CONST DWORD dwSizeOfDataToReceive,
             LPDWORD
                             IpdwSizeOfDataReceived.
             LPBYTE
                             IpbDataReceived,
             LPDWORD
                             IpdwAdditionalErrorCode,
             LPREPLY
                              IpReply
             );
```

Function

Carries out a series of data exchange between the Host Computer and IC card.

Argument & Detailed Function

IpszSerialNumber

Specify the serial number of the objective Card Reader/Writer. The serial number shall be a character string having a NULL at the end.

Refer to ConnectDevice.

dwDataSizeToSend

Specify the size of the data to be sent to the IC card, in bytes.

IpbDataToSend

Specify the top address of the memory area where the data to be sent to the IC card is saved. The data, which starts from the address specified with this argument and whose size is as specified with the argument dwDataSizeToSend, is sent to the IC card.

dwSizeOfDataToReceive

Specify the size of the data to be received from the IC card, in bytes.

The specified data size shall be equal to or less than the data receiving buffer size specified by lpbDataReceived.

Sometimes the data received actually may be less than the size specified by this argument.

IpdwSizeOfDataReceived

Specify a pointer to the variable to save the size in the case of receiving data from the IC card. The size of the data actually received, in bytes, is saved.

IpbDataReceived

Specify the address of the data save destination for saving the data received from the IC card.

IpdwAdditionalErrorCode

When some type of error occurs, the API returns an additional information.

Specify a pointer to the variable to save that.

See "Return Value".

IpReply

Specify the data save destination for the command execution results, and give a pointer to REPLY type data as the save destination.

Refer to REPLY.

As API internal operation, ExecuteCommand gets called. ExecuteCommand is called repeatedly as many times as required. Then the result(s) of only the command executed by the last call is saved in the destination specified by this argument, and it is reported to the Application Program.

In case any halfway ExecuteCommand has got an error, it is determined that the subsequent operation cannot continue anymore and the API itself gets quitted due to the error. Under this situation, returning the result(s) of the command executed by the last call makes it possible to find out the cause the error, with which the API has quitted.

Refer to ExecuteCommand.

For the purpose of writing or reading a parcel of data into or out of the IC card, it can be done to call ExecuteCommand instead as many times as required for causing the same operation effect as this API does. However, since this API includes all the functions to execute chaining the IC card command as the internal processing, it is free from any troublesome factor that chaining the command by manual operation may result in.

Regarding the execution of chaining the IC card control command, refer to the specifications of Card Reader/Writer Interface.

It is forbidden to send a command by executing ExecuteCommand to the objective Card Reader/Writer from another thread in the process of this API. If this operation is done, the result is insecure.

To execute this API, ConnectDevice must have already been completed. Refer to ConnectDevice.

Return Value

_NO_ERROR

Normally completed

_ICC_TRANSMIT_COMMAND_EXECUTION_FAILED_ERROR

ExecuteCommand called in the API internal operation failed.

In this case the variable pointed by lpdwAdditionalErrorCode receives the return value of ExecuteCommand.

Refer to ExecuteCommand.

_ICC_TRANSMIT_NEGATIVE_REPLY_RECEIVED_ERROR

A command executed in the API internal operation returned a negative response.

_ICC_TRANSMIT_FAILED_ALLOCATE_MEMORY_REGION_ERROR

Failed in securing the memory area required for executing this API.

_ICC_TRANSMIT_ABORT_REQUEST_RECEIVED_ERROR

Received an ABORT request from the IC card.

_ICC_TRANSMIT_UNEXPECTED_ERROR

An unexpected error occurred.

Example

```
#define _TIMEOUT
                      (20000)
                                  // milliseconds
CHAR szSerialNumber[ 16];
COMMAND Command;
REPLY Reply;
DWORD dwResult;
// Establishes communications between the Host Computer and the Card Reader/Writer
dwResult = ConnectDevice(
               NULL,
               szSerialNumber
if( dwResult != _NO_ERROR)
   // ConnectDevice failed
   goto _EXIT;
}
// Activates IC card
    Command.bCommandCode = 0x49; // IC card control
    Command.bParameterCode = 0x30; // Activate
    Command.Data.dwSize = 0;
    dwResult = ExecuteCommand(
                  szSerialNumber,
                   Command.
                  _TIMEOUT,
                   &Reply
                  );
    if( dwResult != _NO_ERROR || Reply.replyType != PositiveReply)
       // Command sending failed or command execution failed
       goto _EXIT1;
    }
```

```
// Exchanges data between the Host Computer and IC card
{
    BYTE bDataToSend[] = { 0x10, 0x11, 0x12, 0x13, 0x14, 0x15, 0x16, 0x17, .... };
    WORD dwDataSizeToSend = sizeof( bDataToSend) / sizeof( BYTE);
    BYTE bData[1024];
    WORD dwSizeOfDataReceived;
    DWORD dwErrorCode;
    dwResult = ICCardTransmit(
                   szSerialNumber,
                   dwDataSizeToSend,
                   bDataToSend,
                   512,
                   &dwSizeOfDataReceived,
                   bData.
                   &dwErrorCode,
                   &Reply
                   );
    if( dwResult != _NO_ERROR)
    {
       // ICCardTransmit failed
    }
// Deactivates IC card
    Command.bCommandCode = 0x49; // IC card control
    Command.bParameterCode = 0x31; // Deactivate
    Command.Data.dwSize = 0;
    dwResult = ExecuteCommand(
                   szSerialNumber,
                   Command,
                   _TIMEOUT,
                   &Reply
                   );
    if( dwResult != _NO_ERROR || Reply.replyType != PositiveReply)
       // Command sending failed or command execution failed
    }
}
_EXIT1:
```

CONFIDENTIAL	No	ASL-NP-07652-52	32/4
// Closes communications betwee dwResult = DisconnectDevice(sz		uter and the Card Reader/Writer	
_EXIT:			

SAMTransmit

```
DWORD SAMTransmit(
             LPCSTR
                              IpszSerialNumber.
             COSNT DWORD dwDataSizeToSend,
             LPBYTE
                             IpbDataToSend,
             CONST DWORD dwSizeOfDataToReceive,
             LPDWORD
                             IpdwSizeOfDataReceived.
             LPBYTE
                             IpbDataReceived,
             LPDWORD
                             IpdwAdditionalErrorCode,
             LPREPLY
                              IpReply
             );
```

Function

Carries out a series of data exchange between the Host Computer and SAM.

Argument & Detailed Function

IpszSerialNumber

Specify the serial number of the objective Card Reader/Writer. The serial number shall be a character string having a NULL at the end.

Refer to ConnectDevice.

dwDataSizeToSend

Specify the size of the data to be sent to the SAM, in bytes.

IpbDataToSend

Specify the top address of the memory area where the data to be sent to the SAM is saved. The data, which starts from the address specified with this argument and whose size is as specified with the argument dwDataSizeToSend, is sent to the SAM.

dwSizeOfDataToReceive

Specify the size of the data to be received from the SAM, in bytes.

The specified data size shall be equal to or less than the data receiving buffer size specified by lpbDataReceived.

Sometimes the data received actually may be less than the size specified by this argument.

IpdwSizeOfDataReceived

Specify a pointer to the variable to save the size in the case of receiving data from the SAM. The size of the data actually received, in bytes, is saved.

IpbDataReceived

Specify the address of the data save destination for saving the data received from the SAM.

IpdwAdditionalErrorCode

When some type of error occurs, the API returns an additional information.

Specify a pointer to the variable to save that.

See "Return Value".

IpReply

Specify the data save destination for the command execution results, and give a pointer to REPLY type data as the save destination.

Refer to REPLY.

As API internal operation, ExecuteCommand gets called. ExecuteCommand is called repeatedly as many times as required. Then the result(s) of only the command executed by the last call is saved in the destination specified by this argument, and it is reported to the Application Program.

In case any halfway ExecuteCommand has got an error, it is determined that the subsequent operation cannot continue anymore and the API itself gets quitted due to the error. Under this situation, returning the result(s) of the command executed by the last call makes it possible to find out the cause the error, with which the API has quitted.

Refer to ExecuteCommand.

For the purpose of writing or reading a parcel of data into or out of the SAM, it can be done to call <code>ExecuteCommand</code> instead as many times as required for causing the same operation effect as this API does. However, since this API includes all the functions to execute chaining the SAM command as the internal processing, it is free from any troublesome factor that chaining the command by manual operation may result in.

Regarding the execution of chaining the SAM control command, refer to the specifications of Card Reader/Writer Interface.

It is forbidden to send a command by executing ExecuteCommand to the objective Card Reader/Writer from another thread in the process of this API. If this operation is done, the result is insecure.

To execute this API, ConnectDevice must have already been completed. Refer to ConnectDevice.

Return Value

_NO_ERROR

Normally completed

SAM TRANSMIT COMMAND EXECUTION FAILED ERROR

ExecuteCommand called in the API internal operation failed.

In this case the variable pointed by <code>lpdwAdditionalErrorCode</code> receives the return value of <code>ExecuteCommand</code>.

Refer to ExecuteCommand.

_SAM_TRANSMIT_NEGATIVE_REPLY_RECEIVED_ERROR

A command executed in the API internal operation returned a negative response.

_SAM_TRANSMIT_FAILED_ALLOCATE_MEMORY_REGION_ERROR

Failed in securing the memory area required for executing this API.

_SAM_TRANSMIT_ABORT_REQUEST_RECEIVED_ERROR

Received an ABORT request from the IC card.

_SAM_TRANSMIT_UNEXPECTED_ERROR

An unexpected error occurred.

Example

```
#define _SERIAL_NUMBER
                             "12345678"
                                        // milliseconds
#define _TIMEOUT
                             (20000)
CHAR szSerialNumber[ 16];
COMMAND Command;
REPLY Reply;
DWORD dwResult;
// Establishes communications between the Host Computer and the Card Reader/Writer
dwResult = ConnectDevice(
              _SERIAL_NUMBER,
               szSerialNumber
               );
if( dwResult != _NO_ERROR){
   // ConnectDevice failed
   goto _EXIT;
}
// Selects SAM
    Command.bCommandCode = 0x49; // SAM control
    Command.bParameterCode = 0x50;
                                      // Select SAM
   BYTE Sel = 0x30:
                                      // SAM#1
    Command.Data.dwSize = 1;
                                      // Data size
   Command.Data.lpbBody = &Sel;
                                      // Data
   dwResult = ExecuteCommand(
                  szSerialNumber,
                  Command,
                  _TIMEOUT,
                  &Reply
                  );
```

```
if( dwResult != _NO_ERROR || Reply.replyType != PositiveReply)
    {
       // Command sending failed or command execution failed
       goto _EXIT1;
   }
// Activates SAM
    Command.bCommandCode = 0x49; // SAM control
    Command.bParameterCode = 0x40; // Activate
    Command.Data.dwSize = 0;
    dwResult = ExecuteCommand(
                   szSerialNumber,
                   Command,
                   _TIMEOUT,
                   &Reply
                   );
    if( dwResult != _NO_ERROR || Reply.replyType != PositiveReply)
       // Command sending failed or command execution failed
       goto _EXIT1;
   }
// Exchanges data between the Host Computer and SAM
    BYTE bDataToSend[] = { 0x10, 0x11, 0x12, 0x13, 0x14, 0x15, 0x16, 0x17, .... };
    DWORD dwDataSizeToSend = sizeof( bDataToSend) / sizeof( BYTE);
    BYTE bData[1024];
    DWORD dwSizeOfDataReceived;
    DWORD dwErrorCode;
    dwResult = SAMTransmit(
                    szSerialNumber,
                    dwDataSizeToSend,
                    bDataToSend,
                    512,
                    &dwSizeOfDataReceived,
                    bData,
                    &dwErrorCode,
                    &Reply
                    );
```

```
if( dwResult != _NO_ERROR)
    {
       // SAMTransmit failed
    }
}
// Deactivates SAM
    Command.bCommandCode = 0x49; // SAM control
    Command.bParameterCode = 0x41; // Deactivate
    Command.Data.dwSize = 0;
    dwResult = ExecuteCommand(
                   szSerialNumber,
                   Command,
                   _TIMEOUT,
                   &Reply
                   );
    if( dwResult != _NO_ERROR || Reply.replyType != PositiveReply)
       // Command sending failed or command execution failed
    }
_EXIT1:
// Closes communications between the Host Computer and the Card Reader/Writer
dwResult = DisconnectDevice( szSerialNumber);
_EXIT:
```

CONFIDENTIAL | No | ASL-NP-07652-52 | 38/44

UpdateFirmware

Function

Updates the firmware of the Card Reader/Writer.

Argument & Detailed Function

IpszSerialNumber

Specify the serial number of the objective Card Reader/Writer. The serial number shall be a character string having a NULL at the end.

If only one Card Reader/Writer exists, you might as well specify it with a NULL instead of the serial number.

If a NULL is specified even though two or more Card Reader/Writers exist, it becomes impossible to identify which Card Reader/Writer is the target one so that operation may not work on the Card Reader/Writer you want but work on another one. In such a case, therefore it is prohibited to specify a NULL.

Refer to ConnectDevice

IpszFilename

Specify the name of the file to be downloaded. The file name shall be a character string having a NULL at the end, and it can be accompanied by its path.

fCheckRevision 1 4 1

Determines whether or not to compare the revision of the file specified by *IpszFilename* with the one of firmware installed in the Card Reader/Writer before updating.

In case of TRUE, updating is done only when the revisions are not identical. If the value is FALSE, without comparing the revisions the file is installed replacing a current firmware.

fnFunction

Specify the callback function that is to be called for indicating the percentage of the total process. If you do not need any service like that, specify it with a NULL.

The framework of the callback function has to be the following:

```
VOID WINAPI Func(
    WPARAM wParam, // Indicates the percentage: 0,1,2,...,100
    LPARAM IParam // No function is assigned
)
{
    ...
    ...
}
```

39/44

The percentage is provided as a value of wParam varying from 0 to 100, and the callback function is called only when the value of the percentage increased.

There is no function assigned to 1Param.

IpdwAdditionalErrorCode

When some type of error occurs, the API returns an additional information.

Specify a pointer to the variable to save that.

See "Return Value".

When this API is executed, operation is carried out in due order as the following list describes:

Order of operation	Purpose	What is executed	Descriptions	
	To commence communication	ConnectDevice		
	To distinguish Supervisor mode & User mode	Initialize command	If it is notified to be Supervisor mode, the operation jumps to step . If it is User mode, the operation switches to Supervisor mode by steps ~ .	
	To switch to Supervisor mode	Switch command	By executing this command, Plug & Play operation occurs.	
	To terminate communication	DisconnectDevice	Since Plug & Play operation occurs, communication-commencing operation is	
	To commence communication	ConnectDevice	carried out again.	
	To initialize the Card Reader/Writer	Initialize command		
	To transmit download data	Download command	Step gets repeated to download all data.	
	To switch to User mode	Switch command	By executing this command, Plug & Play operation occurs.	
	To terminate communication	DisconnectDevice	Since Plug & Play operation occurs, communication-commencing operation is	
	To commence communication	ConnectDevice	carried out again.	
	To make sure that the firmware has been updated correctly	Initialize command	It is checked that a positive response gets returned to this command, to make sure that the "User Program Code Area" is operating.	
	To terminate communication	DisconnectDevice		

As ConnectDevice and DisconnectDevice are executed in the internal operation of this API, you do not need to execute ConnectDevice to establish communications between the Host Computer and the objective Card Reader/Writer before executing this API. If ConnectDevice has finished, execute DisconnectDevice first and then execute this API.

It is forbidden to access to or to control the objective Card Reader/Writer of this API in the process by executing any API such as ConnectDevice, DisconnectDevice, ExecuteCommand, and CancelCommand. If this operation is done, the result is insecure.

Return Value

_NO_ERROR

Normally completed

_UPDATE_FIRMWARE_CONNECT_DEVICE_FAILED_ERROR

ConnectDevice called in the API internal operation failed.

In this case the variable pointed by <code>lpdwAdditionalErrorCode</code> receives the return value of <code>ConnectDevice</code>.

Refer to ConnectDevice.

_UPDATE_FIRMWARE_DISCONNECT_DEVICE_FAILED_ERROR

DisconnectDevice called in the API internal operation failed.

In this case the variable pointed by lpdwAdditionalErrorCode receives the return value of DisconnectDevice.

Refer to DisconnectDevice.

_UPDATE_FIRMWARE_UNKNOWN_FILE_TYPE_ERROR

Unknown type of file was specified. This API does not know how to handle the file.

_UPDATE_FIRMWARE_CANNOT_OPEN_FILE_ERROR

The file cannot get opened.

_UPDATE_FIRMWARE_FAILED_TO_ALLOCATE_MEMORY_REGION_ERROR

Failed in securing the memory area for saving the download file.

_UPDATE_FIRMWARE_CANNOT_READ_FILE_ERROR

An error has happened at the time of reading the file.

_UPDATE_FIRMWARE_UNEXPECTED_FILE_CONTENTS_ERROR

The file cannot get interpreted.

_UPDATE_FIRMWARE_DEVICE_ALREADY_CONNECTED_ERROR

Communications between the Host Computer and the objective Card Reader/Writer has been established.

_UPDATE_FIRMWARE_COMMAND_EXECUTION_FAILED_ERROR

ExecuteCommand called in the API internal operation failed.

In this case the variable pointed by <code>lpdwAdditionalErrorCode</code> receives the return value of <code>ExecuteCommand</code>.

Refer to ExecuteCommand.

_UPDATE_FIRMWARE_NEGATIVE_REPLY_RECEIVED_ERROR

A command executed in the API internal operation returned a negative response.

41/44

_UPDATE_FIRMWARE_IDENTICAL_REVISION_ERROR

The revision number of the file specified by <code>lpszFilename</code> is identical with the one of the current firmware.

_UPDATE_FIRMWARE_UNEXPECTED_ERROR

An unexpected error occurred.

Example

```
E.g. 1)
static CHAR szSerialNumber[] = "12345678";
DWORD dwErrorCode;
// Updates firmware
DWORD dwResult = UpdateFirmware(
                         szSerialNumber, // Objective Card Reader/Writer's serial number
                         "1234-56A.DWL", // File to download into the Card Reader/Writer
                         TRUE.
                                           // Compares revision numbers
                         NULL,
                                           // No information about progress is required
                         &dwErrorCode
                                          // Additional error information is returned if needed
                         );
E.g. 2)
BOOL g_flnTheProcess = FALSE;
// Callback function
void WINAPI Func( WPARAM wParam, LPARAM IParam)
    if(wParam == 0)
    {
        // Firmware updating process has just begun
        g_fInTheProcess = TRUE;
    }
    else if( wParam == 100)
        // Firmware updating process has ended
        g_fInTheProcess = FALSE;
   }
}
```

```
ASL-NP-07652-52
```

```
void Sample(void)
{
    static CHAR szFilename[] = "c:\\users\\systemfiles\\1234-56A.dwl";
    DWORD dwErrorCode;
   // Updates firmwate
    DWORD dwResult = UpdateFirmware(
                             NULL,
                                          // Just one Card Reader/Writer is installed
                             szFilename,
                             FALSE,
                             ( CALL_BACK_FUNCTION)Func,
                             &dwErrorCode
                             );
}
```

4.2.4 Log file

 ${\tt CollectLogEx.dll} \ \ \textbf{is the DLL to create a log file}.$

The features of CollectLogEx.dll and the log file created by the DLL are the followings:

	Item	Features
[4]	File format	Format: Text file
ניין	File format	Symbol of line breaks: CR,LF (linefeed-carriage return character pairs) Symbol of an end of file: Not used
[2]	File name	\$LogEx.txt
		The following registry enables you to modify the setting: Registry: HKEY_LOCAL_MACHINE\SOFTWARE\SankyoCollectLogEx Key: LogFileName (REG_SZ)
[3]	Folder to create a log	Current directory
	file	The following registry enables you to modify the setting: Registry: HKEY_LOCAL_MACHINE\SOFTWARE\SankyoCollectLogEx Key: LogFileFolder (REG_SZ)
[4]	Maximum number of	10,000
	lines	The following registry enables you to alter the setting of the value: Registry: HKEY_LOCAL_MACHINE\SOFTWARE\SankyoCollectLogEx Key: MaxNumOfLines (REG_DWORD)
		Range of the value: from 1 to 100,000 (If the value set is out of range, 10,000 is applied.)
		Note: When the line number exceeds the value specified by "maximum number of lines", it returns to the first line and keeps recording logs putting new lines over existing ones.
[5]	Number of characters	100
	per line	The following registry enables you to alter the setting of the value: Registry: HKEY_LOCAL_MACHINE\SOFTWARE\SankyoCollectLogEx Key: MaxNumOfCharactersPerLine (REG_DWORD)
		Range of the value: from 100 to 256 (If the value set is out of range, 100 is applied.)
[6]	Maximum size of the file	The following calculation gives the size in bytes: (maximum number of lines)x{(number of characters per line)+2}
[7]	Capability of disabling the DLL to create a log	If there is no CollectLogEx.dll installed, no log file is to be created.
	file	Note: Even without installation of CollectLogEx.dll, the DLL can still work. However, under such condition, no log file is created. When log file creating operation itself seems to cause a security problem because any created log file may drain away by mistake to disclose the contents of transaction, it might be better not to install CollectLogEx.dll or to uninstall it if it is already installed.
[8]	Identification of the	The marker line, which is filled with '~', is made to show the newest
	latest recorded line	line in a log file, and it facilitates searching the position of the line.

CONFIDENTIAL	No	ASL-NP-07652-52	44/44
The end of this document.			